

COMAP reduce docs]COMAP Memo 0: COMAP Manchester
Reduction Pipeline Documentation

[

Stuart Harper

March 5, 2019

Contents

1	Installation	3
2	Usage	3
2.1	Parameter Files	3
3	Classes	4
3.1	BaseClass.H5Data	4

1 Installation

Requirements:

- PYTHON 3.0 or higher.
- Compiled shared libraries of the FORTRAN version of the Starlink astronomical libraries (SLALIB) available from <http://starlink.eao.hawaii.edu/starlink/2018ADownload>.
- A copy of parallel ready H5Py. Installation instructions can be found here <http://docs.h5py.org/en/stable/mpi.html>. N.B.: If you are using an Anaconda packaged version of PYTHON installation you may need to remove the existing CONDA install of HDF5.
- The latest version of HEALPY and MPI4PY (either openMPI or MPICH work as backends).

To install the Manchester COMAP reduction pipeline:

- Clone/download the github repository found here: <https://github.com/SharperJBCA/COMAPreduce>.
- Enter the directory: `cd COMAPreduce` and run `python setup.py install`. If your SLALIB libraries are not in standard location you must define the environment variable: `SLALIB_LIBS`
- To run the COMAP pipeline make a new directory above COMAPreduce (e.g. `cd ../ && mkdir runcomapreduce`) and copy the `RUN.PY`, and `.INI` files there.
- The pipeline can then be run using the command: `mpirun -n X python run.py -F FILELIST.list -P PARAMETERS.ini`. `FILELIST.list` should contain a list of files with either just the filenames to be processed or the full path to files to be processed. `PARAMETERS.ini` will control the processing to be performed, details of which are described in Sections 2 and 3.

2 Usage

2.1 Parameter Files

There are several example parameter files already included:

- AMBLOAD.INI - This will calculate the T_{sys} and gain (e.g. volts per Kelvin) from ambient load stare observations.
- DOWNSAMPLE.INI - This will downsample a data file in frequency by `factor` times and also check to see if any pointing needs to be added.
- FITJUPITER.INI - This will fix the pointing, downsample, and calibrate a Jupiter observation to the ambient load. Then it will fit a Gaussian to the time ordered data to derive amplitude, pointing and beam width measurements. It will also produce a calibration scale in units of Janskys/Kelvin for every horn and frequency channel.

3 Classes

3.1 BaseClass.H5Data

Useful functions for defining new classes:

- `getdset` - Retrieve a dataset, if it is not in memory load it.
- `setdset` - Load a dataset into memory.
- `resizedset` - Resize a dataset by passing it a new array.
- `updatedset` - Update a dataset values.
- `getAttr` - Get an attribute (stored in output file)
- `setAttr` - Set an attribute
- `getextra` - Get a dataset from the extra outputs
- `setextra` - Set an array to be assigned to extra outputs (must describe the shape of the array, e.g. which axis refers to horns, frequencies, etc...)
- `resizeextra` - Change dimensions of an extra dataset.

N.B. Never write directly to the `dset` or `extras` attributes of the `H5Data` class.

Useful attributes/functions for MPI routines:

- `splitType` - Axis type being split for MPI purposes (i.e., either `Types._HORNS_`, `Types._SIDEBANDS_`, `Types._FREQUENCY_`, `Types._TIME_`).

- selectType - Axis type being explicitly selected (i.e., as above)
- selectIndex - Index being selected along selectType axis.
- splitFields - Names of fields in COMAP data structure that will contain a split axis.
- selectFields - Names of fields in COMAP data structure that will have a selected axis.
- hi/lo - Dictionary, for each splitField, defining where in the larger structure this process is accessing data.
- ndims - Dictionary containing dimensions of each dataset in memory for this process.
- fullFieldLengths - Dictionary containing dimensions of each dataset in memory in total.
- getDataRange - Function that returns how to split N values between M processes.